KEY NAMES:

	ALTO I	ALTO II
CANCEL	upper-right blank	BW
COM	lower-right blank	lower-left, upper-right, or lower-right blank
DO	ESC	ESC
PASTE	LF	LF
NEXT	middle blank	next-to-bottom blank

SCROLLING:

Scroll bar is on extreme left. Thumb bar is at top of editor window.

Scroll UP with Left button; places adjacent text at window top.

Scroll DOWN with right button; moves top of window adjacent to cursor.

Thumb with middle button by pointing at relative position on thumb bar.

Thumb marker indicates relative position of target in text.

THE MOUSE:

Left — Caret is inserted at
Middle — end of item nearest cursor
Right

Left
Middle
Right

MOUSE BUTTONS PLUS SHIFT AND/OR CONTROL KEYS:

	IN TEXT AREA/IN LINE BAR
Shift +Left:	select CHARACTER/LINE as source
CTRL+Left:	select CHARACTER/LINE for deletion
CTRL+Shift+Left:	select CHARACTER/LINE for move
Shift +Middle:	select WORD/PARAGRAPH as source
CTRL+Middle:	select WORD/PARAGRAPH for deletion
CTRL+Shift+Middle:	select WORD/PARAGRAPH for move
Shift +Right:	extend source selection
CTRL+Right:	extends selection for deletion
CTRL+Shift+Right:	extend move selection

Single Click Actions:
IN TEXT AREA/IN LINE BAR

Left	Select CHARACTER/LINE as target
Middle	Select WORD/PARAGRAPH as target
Right	Extend selection
+Shift	make source selection
+CTRL	make pending delete selection

Multiple Click Actions:

Extend selection up thru hierarchy
Extend selection up thru hierarchy
Reduces selection down thru hierarchy

Selection hierarchy is:
character, word, line,
paragraph, everything

TAPPING Control while Shift or mouse button depressed
will toggle pending delete of selections
Pressing CANCEL before releasing all buttons will nullify acti

COMMAND KEYS (to invoke commands, hold down COM and strike the command key:)

a: Place caret after selection.

b: Bracket target selection with placeholders

d: Delete target selection.

e: Everything. Select everything as pending delete.

f: Find. Type or select string for search. Accepts * for wild card matches.

g: Get. Type or select file name. Contents of file is inserted at caret.

i: Place caret before selection.

p: Put. Type or source select file name. Puts selected text into file.

r: Replace. Delete target selection (for modal editor compatibility).

s: Substitute. Type or source select new text, then old text. Accepts * for wild card matches in FOR string.

t: Time. Insert date/time at caret.

u: Undo. Undoes previous commands. See CANCEL.

' " ([{ Bracket target selection with specified bracket type.

0, 1, ... , 9: Set window boundaries to pre-set positions.

OTHER COMMANDS   (see Key Names above)

	WITHOUT COM	WITH COM
BS:	delete previous character	delete previous word
Shift+BS:	delete next character	delete next word
CTRL+W:	delete previous word	
CTRL+Shift+W:	delete next word	
DEL:	Delete target selection. Same as COM+D.	
DO (ESC):	repeats previous text action (not selection actions), IF TARGET SELECTION EXISTS. ELSE, no operation.	
CANCEL:	same as COM+U. Undoes previous cancellable sequence.	
PASTE(LF):	Insert the previously deleted text at caret.	
NEXT:	Pending delete select the text between the next two placeholders.	

LAUREL MODELESS EDITOR COMMAND SUMMARY – 6T24